Package: hbsae (via r-universe)

October 18, 2024

Version 1.2 License GPL-3

Title Hierarchical Bayesian Small Area Estimation

Type Package
LazyLoad yes
Encoding UTF-8

Description Functions to compute small area estimates based on a basic area or unit-level model. The model is fit using restricted maximum likelihood, or in a hierarchical Bayesian way. In the latter case numerical integration is used to average over the posterior density for the between-area variance. The output includes the model fit, small area estimates and corresponding mean squared errors, as well as some model selection measures. Additional functions provide means to compute aggregate estimates and mean squared errors, to minimally adjust the small area estimates to benchmarks at a higher aggregation level, and to graphically compare different sets of small area estimates.

Date 2022-03-03

Depends R (>= 2.15.2)

Imports Matrix, methods

Suggests mcmcsae, survey, knitr, hypergeo, testthat

RoxygenNote 7.1.2 **NeedsCompilation** no

Author Harm Jan Boonstra [aut, cre]

Maintainer Harm Jan Boonstra <hjboonstra@gmail.com>

Date/Publication 2022-03-05 15:40:13 UTC **Repository** https://hjboonstra.r-universe.dev **RemoteUrl** https://github.com/cran/hbsae

RemoteRef HEAD

RemoteSha 558d4724b10b728ae64ba1aa9dad835494cb81ba

2 aggr

Contents

hbsae-package		A package for hierarchical Bayesian small area estimation.				
Index			22			
	uweights		20			
	_					
	-					
	•					
	fSurvReg		14			
	fSAE.Unit		10			
	fSAE.Area		9			
	fSAE		7			
	CVarea		5			
	bench		3			
	aggr		2			
	hbsae-package		2			

Description

Package hbsae provides functions to compute small area estimates based on the basic unit-level and area-level models. The models are fit and small area estimates are computed in a hierarchical Bayesian way, using numerical integration.

Details

The main function that does most of the computational work is fSAE.Unit. Function fSAE is provided as a more convenient interface to fSurvReg, fSAE.Area and fSAE.Unit.

aggr

Compute aggregates of small area estimates and MSEs.

Description

Compute aggregates of small area estimates and MSEs.

Usage

aggr(x, R)

bench 3

Arguments

x sae object.

R aggregation matrix, M x r matrix where M is the number of areas and r the number of aggregate areas; default is aggregation over all areas.

Value

Object of class sae with aggregated small area estimates and MSEs.

See Also

```
sae-class
```

Examples

```
d <- generateFakeData()

# compute small area estimates
sae <- fSAE(y0 ~ x + area2, data=d$sam, area="area", popdata=d$Xpop)

# by default aggregate over all areas
global <- aggr(sae)
EST(global); RMSE(global)

# aggregation to broad area
# first build aggregation matrix
M <- d$Xpop[, c("area22", "area23", "area24")] / d$Xpop[, "(Intercept)"]
M <- cbind(1 - rowSums(M), M); colnames(M)[1] <- "area21"
est.area2 <- aggr(sae, M)
EST(est.area2); RMSE(est.area2)
COV(est.area2) # covariance matrix</pre>
```

bench

Benchmark small area estimates.

Description

Benchmark small area estimates to conform to given totals at aggregate levels.

Usage

```
bench(x, R, rhs, mseMethod = "no", Omega, Lambda)
```

4 bench

Arguments

R restriction matrix, M x r matrix where r is the number of restrictions and M the number of areas; default is a single constraint on the population total. Note that R acts on the vector of area totals, not the vector of means. r-vector of benchmark totals corresponding to the restrictions represented by (the columns of) R. mseMethod if "no", MSEs are not updated, if "exact", constraints are treated as independent information (exact identities by default), and if "model", the squared differences between original and benchmarked estimates are added to the MSEs. Omega M x M matrix Ω in objective function, see details. By default this is the covariance matrix of the small area estimates. Lambda r x r matrix Λ in objective function, see details. By specifying Lambda it is possible to impose 'soft' constraints, i.e. constraints that need to hold only approximately.	X	sae object to be benchmarked. As an alternative, a list can be supplied with at least components Narea with area population sizes and est with small area estimates. In the latter case argument Omega cannot be left unspecified.
 (the columns of) R. mseMethod if "no", MSEs are not updated, if "exact", constraints are treated as independent information (exact identities by default), and if "model", the squared differences between original and benchmarked estimates are added to the MSEs. Omega M x M matrix Ω in objective function, see details. By default this is the covariance matrix of the small area estimates. Lambda r x r matrix Λ in objective function, see details. By specifying Lambda it is possible to impose 'soft' constraints, i.e. constraints that need to hold only ap- 	R	number of areas; default is a single constraint on the population total. Note that
 dent information (exact identities by default), and if "model", the squared differences between original and benchmarked estimates are added to the MSEs. Omega M x M matrix Ω in objective function, see details. By default this is the covariance matrix of the small area estimates. Lambda r x r matrix Λ in objective function, see details. By specifying Lambda it is possible to impose 'soft' constraints, i.e. constraints that need to hold only ap- 	rhs	
ance matrix of the small area estimates. Lambda $r \times r$ matrix Λ in objective function, see details. By specifying Lambda it is possible to impose 'soft' constraints, i.e. constraints that need to hold only ap-	mseMethod	dent information (exact identities by default), and if "model", the squared dif-
possible to impose 'soft' constraints, i.e. constraints that need to hold only ap-	Omega	· · · · · · · · · · · · · · · · · · ·
	Lambda	possible to impose 'soft' constraints, i.e. constraints that need to hold only ap-

Details

This function adjusts the small area estimates EST(x), denoted by x_0 , to

$$x_1 = x_0 + \Omega R_N (R'_N \Omega R_N + \Lambda)^{-1} (t - R'_N x_0),$$

where

- Ω is a symmetric M x M matrix. By default, Ω is taken to be the covariance matrix V_0 of the input sae-object x.
- $R_N = \operatorname{diag}(N_1, \dots, N_M) R$ where R is the matrix passed to bench and N_i denotes the population size of the ith area, is a M x r matrix describing the aggregate level relative to the area level. Note that the matrix R acts on the vector of area totals whereas R_N acts on the area means to produce the aggregate totals. The default for R is a column vector of 1s representing an additivity constraint to the overall population total.
- t is an r-vector of aggregate-level totals, specified as rhs, that the small area estimates should add up to.
- Λ is a symmetric r x r matrix controlling the penalty associated with deviations from the constraints $R'_N x_1 = t$. The default is $\Lambda = 0$, implying that the constraints must hold exactly.

The adjusted or benchmarked small area estimates minimize the expectation of the loss function

$$L(x_1, \theta) = (x_1 - \theta)' \Omega^{-1}(x_1 - \theta) + (R'_N x_1 - t)' \Lambda^{-1}(R'_N x_1 - t)$$

with respect to the posterior for the unknown small area means θ .

Optionally, MSE(x) is updated as well. If mseMethod="exact" the covariance matrix is adjusted from V_0 to

$$V_1 = V_0 - V_0 R_N (R'_N \Omega R_N + \Lambda)^{-1} R'_N V_0,$$

CVarea 5

and if mseMethod is "model" the adjusted covariance matrix is

$$V_1 = V_0 + (x_1 - x_0)(x_1 - x_0)'.$$

The latter method treats the benchmark adjustments as incurring a bias relative to the best predictor under the model.

Value

An object of class sae with adjusted estimates.

References

G.S. Datta, M. Ghosh, R. Steorts and J. Maples (2011). Bayesian benchmarking with applications to small area estimation. TEST 20(3), 574-588.

Y. You, J.N.K. Rao and P. Dick (2004). Benchmarking Hierarchical Bayes Small Area Estimators in the Canadian Census Undercoverage Estimation. Statistics in Transition 6(5), 631-640.

See Also

```
sae-class
```

Examples

```
d <- generateFakeData()

# compute small area estimates
sae <- fSAE(y0 ~ x + area2, data=d$sam, area="area", popdata=d$Xpop)

# calibrate to overall population total
sae.c <- bench(sae, rhs=sum(d$mY0*sae$Narea))
plot(sae, sae.c)</pre>
```

CVarea

Compute area-level cross-validation measure for sae objects.

Description

This function computes a cross-validation measure defined at the area level. It can be used, for example, to compare the predictive ability of area and unit-level models. The code is based in part on that of cv.glm from package **boot**.

6 CVarea

Usage

```
CVarea(
   sae,
   weight = TRUE,
   cost = function(y, yhat, w) sum(w * (y - yhat)^2)/sum(w),
   K = 10L,
   method = "hybrid",
   seed
)
```

Arguments

sae	object of class sae, resulting from a call to fSAE, fSAE.Area, or fSAE.Unit.
weight	if TRUE, use weights inversely proportional to the MSEs of \boldsymbol{y} - yhat in the cost function.
cost	cost function to be used. Defaults to a quadratic cost function.
K	K in K-fold cross-validation. Specifies in how many parts the dataset should be divided.
method	method used to refit the model. One of "HB", "hybrid" (default) or "REML", in the order of slow to fast.
seed	random seed used in selecting groups of areas to leave out in K-fold cross-validation.

Value

The computed area-level cross-validation measure.

Examples

fSAE 7

fSAE	Fit a linear model with random area effects and compute small area estimates.

Description

This function prepares the (unit-level) input data and calls one of the lower level functions fSurvReg, fSAE.Area or fSAE.Unit to compute survey regression, area-level model or unit-level model small area estimates. Area-level model estimates are computed by first computing survey regression estimates and using these as input for fSAE.Area.

Usage

```
fSAE(
  formula,
  data,
  area = NULL,
  popdata = NULL,
  type = "unit",
  model.direct = NULL,
  formula.area = NULL,
  contrasts.arg = NULL,
  remove.redundant = TRUE,
  redundancy.tol = 1e-07,
  sparse = FALSE,
  ...
)
```

Arguments

formula	model formula, indicating response variable and covariates.
data	unit-level data frame containing all variables used in formula, area and formula. area arguments. These variables should not contain missing values.
area	name of area indicator variable in data; if NULL, no random effects are used in the model.
popdata	data frame or matrix containing area population totals for all covariates. The rows should correspond to areas for which estimates are required. Column names should include those produced by model.matrix(formula, data, contrasts.arg), up to permutations of the names in interactions. A column named '(Intercept)' is required and should contain the area population sizes. If popdata is NULL, only the model fit is returned.
type	type of small area estimates: "direct" for survey regression, "area" for area-level model, "unit" for unit-level model estimates. If type is "data" then only the data

including the model matrix and population means are returned.

8 fSAE

model.direct

if type="area", this argument can be used to specify by means of a formula the covariates to use for the computation of the initial survey regression estimates. If unspecified, the covariates specified by formula are used both at the unit level (for the initial estimates) and at the area level (for the area-level model estimates).

formula.area

if type="unit", this is an optional formula specifying covariates that should be used at the area level. These covariates should be available in popdata.

contrasts.arg 1
remove.redundant

list for specification of contrasts for factor variables. Passed to ${\tt model.matrix}$.

if TRUE redundant columns in the design matrix are removed. A warning is issued if the same redundancy does not show also in the corresponding population totals. In the case of the area-level model there may still be redundancy at the area level.

redundancy.tol

tolerance for detecting linear dependencies among the columns of the design matrix. Also used as tolerance in the check whether the design matrix redundancy is shared by the population totals.

sparse

if TRUE sparse.model.matrix (package Matrix) is used to compute the covariate design matrix. This can be efficient for large datasets and a model containing categorical variables with many categories.

additional arguments passed to fSAE. Unit or fSurvReg.

Value

An object of class sae containing the small area estimates, their MSEs, and the model fit. If type is "data" a list containing the model matrix, response vector, area indicator, area population sizes and matrix of population means is returned.

See Also

```
sae-class
```

Examples

fSAE.Area 9

```
method="REML", silent=TRUE)
plot(saeHB, saeREML) # compare
# basic area-level model
saeA <- fSAE(y0 \sim x + area2, data=d\$sam, area="area", popdata=d\$Xpop,
             type="area")
plot(saeHB, saeA)
# SAE estimates based on a linear unit-level model without area effects
saeL <- fSAE(y0 ~ x + area2, data=d$sam, area="area", popdata=d$Xpop,</pre>
             method="synthetic")
plot(saeHB, saeL)
# model-based estimation of overall population mean without area effects
est.global <- fSAE(y0 ~ x + area2, data=d$sam, area=NULL,
                   popdata=colSums(d$Xpop), method="synthetic")
EST(est.global); RMSE(est.global)
# no model fitting or estimation, but return design matrix, variable of interest,
    area indicator, area population sizes and matrix of population means
dat <- fSAE(y0 ~ x + area2, data=d$sam, area="area", popdata=d$Xpop,</pre>
            type="data")
str(dat)
```

fSAE.Area

Compute small area estimates based on the basic area-level model.

Description

This function returns small area estimates based on the basic area-level model, also known as the Fay-Herriot model. It calls fSAE. Unit to carry out the computations.

Usage

```
fSAE.Area(est.init, var.init, X, x, ...)
```

Arguments

est.init

m-vector of initial estimates, where m is the number of in-sample areas.

var.init

m-vector of corresponding variance estimates.

Χ

M x p matrix of area-level covariates (typically population means), where M is the number of areas for which estimates are computed. If missing, a column vector of ones of the same length as $\verb|est.init|$ is used, corresponding to a model with an intercept only. The M areas may or may not equal the m areas for which initial estimates are provided. For example, estimates for out-of-sample areas, for which no initial estimates are available, are computed as long as the corresponding rows of auxiliary means are in X. It is also possible to compute estimates only for a subset of sample areas, see the help for argument x.

x an optional m x p matrix with auxiliary area-level covariates to be used for fitting the model, where the rows correspond to the components of est.init. If the M areas corresponding to the rows of X do not contain all m areas corresponding to est.init, x must be provided separately in order to be able to fit the model.

additional arguments passed to fSAE.Unit. For example, passing an M-vector Narea with area population sizes (along with the matrix X of population means) allows to compute aggregates of the small area estimates. See the documentation of function fSAE.Unit for a description of other possible arguments.

Value

An object of class sae containing the small area estimates and MSEs, the model fit, and model selection measures.

References

R.E. Fay and R.A. Herriot (1979). Estimates of Income for Small Places: An Application of James-Stein Procedures to Census Data. Journal of the American Statistical Association 74(366), 269-277. J.N.K. Rao and I. Molina (2015). Small Area Estimation. Wiley.

See Also

```
sae-class
```

Examples

fSAE.Unit

Compute small area estimates based on the basic unit-level model.

Description

This is the function that carries out most of the computational work. It computes small area estimates based on the basic unit-level model, also known as the Battese-Harter-Fuller model, although it is also called by fSurvReg and fSAE. Area to compute survey regression or area-level model small area estimates. By default, Hierarchical Bayes estimates are computed, using fast one-dimensional numerical integration to average over the posterior density for the ratio of between and within area

variance. This way, the small area estimates and MSEs account for the uncertainty about this parameter. Besides hierarchical Bayes, REML and hybrid methods are supported. These methods use the REML estimate or posterior mean of the variance ratio, respectively, as a plug-in estimate. Both methods do not account for uncertainty about this parameter. Synthetic estimates are computed by setting the variance ratio to zero.

Usage

```
fSAE.Unit(
 у,
 Χ,
 area,
 Narea = NULL,
 Xpop = NULL,
  fpc = TRUE,
  v = NULL,
  vpop = NULL,
 w = NULL,
 wpop = NULL,
 method = "HB",
 beta0 = rep(0, ncol(X)),
 Omega0 = Diagonal(n = ncol(X), x = 0),
  nu0 = 0,
  s20 = 0,
  prior = function(x) rep.int(1L, length(x)),
 CV = prod(dim(X)) < 1e+06,
 CVweights = NULL,
  silent = FALSE,
 keep.data = FALSE,
  full.cov = nrow(Xpop) < 1000L,
 lambda0 = NULL
 rel.int.tol = 0.01,
)
```

Arguments

У	response vector of length n.
X	n x p model matrix.
area	n-vector of area codes, typically a factor variable with m levels, where m is the number of in-sample areas.
Narea	M-vector of area population sizes, where M is the number of areas for which estimates are required. There should be a one-to-one correspondence with the rows of Xpop. This argument is required unless Xpop=NULL or fpc=FALSE.
Хрор	$M\ x\ p$ matrix of population means. If Xpop is not provided, only the model fit is returned.
fpc	whether a finite population correction should be used. Default is TRUE.

unit-level variance structure, n-vector. Defaults to a vector of 1s. In some cases it might be useful to take v proportional to the sampling probabilities.

vpop population area means of v, M-vector. Defaults to a vector of 1s. Not used when

fpc is FALSE.

method

area-level variance structure, m-vector. Defaults to a vector of 1s.

wpop area-level variance structure, M-vector. Defaults to a vector of 1s. Only compo-

nents of wpop corresponding to out-of-sample areas are actually used.

one of "HB", "hybrid", "REML", "synthetic", "survreg", "BLUP" where "HB"

(default) does the full hierarchical Bayes computation, i.e. numerical integration over the posterior density for the between area variance parameter, "hybrid" computes the Best Linear Unbiased Predictor (BLUP) with the posterior mean for the variance parameter plugged in, "REML" computes the BLUP with the restricted maximum likelihood estimate of the variance parameter plugged in, "synthetic" computes synthetic estimates where the between area variance is set to 0, and "survreg" computes survey regression estimates where the between area variance approaches infinity. "BLUP" computes BLUP estimates with the value provided for lambda0 as a fixed plug-in value for the ratio of between and within area variance. Only method "HB" takes uncertainty about the between-

area variance into account.

beta0 mean vector of normal prior for coefficient vector.

Omega0 inverse covariance matrix of normal prior for coefficient vector. Default prior

corresponds to the (improper) uniform distribution.

nu0 degrees of freedom parameter for inverse gamma prior for residual (within-area)

variance. Default is 0.

scale parameter for inverse gamma prior for residual (within-area) variance. De-

fault is 0.

prior prior density for the ratio lambda = between-area-variance / within-area vari-

ance. This should be a (vectorized) function that takes a vector lambda and returns a vector of prior density values at lambda. The density does not have to be normalized. The default is the (improper) uniform prior. The within-area

variance and lambda are assumed independent a priori.

CV whether (an approximation to the) leave-one-out cross-validation measure should

be computed. As this requires the computation of a dense matrix the size of X, the default is to set CV to FALSE if the size of X is larger than a certain lower

bound.

CVweights n-vector of weights to use for CV computation.

silent if FALSE, plot the posterior density for the variance ratio.

keep.data if TRUE return the input data (y,X,area,Xpop). This is required input for the

cross-validation function CVArea.

full.cov if TRUE compute the full covariance matrix for the small area estimates. The

computed correlations do not account for uncertainty about the variance ratio.

lambda0 optional starting value for the ratio of between and within-area variance used in

the numerical routines. If method="BLUP" then this value will instead be used

as a fixed plug-in value.

rel.int.tol tolerance for the estimated relative integration error (default is 1 percent). A warning is issued if the estimated relative error exceeds this value.

... additional control parameters passed to function integrate.

Details

The default Hierarchical Bayes method uses numerical integration (as provided by function integrate) to compute small area estimates and MSEs. The model parameters returned, such as fixed and random effects, are currently not averaged over the posterior distribution for the variance ratio. They are evaluated at the posterior mean of the variance ratio.

Value

An object of class sae containing the small area estimates and MSEs, the model fit, and model selection measures.

References

G.E. Battese, R.M. Harter and W.A. Fuller (1988). An Error-Components Model for Prediction of County Crop Areas Using Survey and Satellite Data. Journal of the American Statistical Association, 83(401), 28-36.

G.S. Datta and M. Ghosh (1991). Bayesian Prediction in Linear Models: Applications to Small Area Estimation. The Annals of Statistics 19(4), 1748-1770.

J.N.K. Rao and I. Molina (2015). Small Area Estimation. Wiley.

See Also

```
sae-class
```

Examples

14 fSurvReg

fSurvReg Compute small area estimates based on the survey regression estimator.	:=
---	----

Description

This function computes survey regression estimates as a special case of unit-level model small area estimates with a (relatively) very large value for the between-area variance but without including area effects in the model fit. The model assumes a single overall variance parameter, so that the resulting estimated variances are not area-specific but smoothed. Varying inclusion probabilities may be taken into account by including them in the model, e.g. as an additional covariate, and/or as model variance structure by specifying arguments v and vpop, see fSAE.Unit. The resulting estimates may be used as input estimates for area-level model small area estimation.

Usage

```
fSurvReg(y, X, area, Narea, Xpop, removeEmpty = TRUE, ...)
```

Arguments

	0.1
V	response vector of length n.
.у	response vector of length ii.

X n x p model matrix.

area n-vector of area codes, typically a factor variable with m levels, where m is the

number of in-sample areas.

Narea M-vector of area population sizes.

Xpop M x p matrix of population means.

removeEmpty whether out-of-sample areas should be removed from the results. If FALSE these

areas are retained in the vectors of estimates, but they will have (relatively) very

large standard errors.

... optional arguments v and vpop passed to fSAE. Unit.

Value

An object of class sae containing the survey regression small area estimates and their estimated variances.

References

G.E. Battese, R.M. Harter and W.A. Fuller (1988). An Error-Components Model for Prediction of County Crop Areas Using Survey and Satellite Data. Journal of the American Statistical Association, 83(401), 28-36.

J.N.K. Rao and I. Molina (2015). Small Area Estimation. Wiley.

See Also

```
sae-class
```

generateFakeData 15

Examples

generateFakeData

Generate artificial dataset for demonstration and testing purposes.

Description

Generate artificial dataset for demonstration and testing purposes.

Usage

```
generateFakeData(
    M = 50,
    meanNarea = 1000,
    sW = 100,
    sB = 50,
    sBx = 0.5,
    samplingFraction = 0.1
)
```

Arguments

M number of areas.
 meanNarea mean number of population units per area.
 sW within area standard deviation.
 sB between area standard deviation.
 sBx random slope standard deviation.

samplingFraction

sampling fraction used to draw a random sample from the population units.

Value

List containing sample (sam), population totals (Xpop), and true population means for four target variables (mY0, mY1, mY2, mY3).

16 plot.sae

plot.sae

Plot method for objects of class sae.

Description

This function plots small area estimates with error bars. Multiple sets of estimates can be compared. The default ordering of the estimates is by their area population sizes. This method uses a plot function that is adapted from function coefplot.default of package **arm**.

Usage

```
## $3 method for class 'sae'
plot(
    ...,
    n.se = 1,
    est.names,
    sort.by = NULL,
    decreasing = FALSE,
    index = NULL,
    maxrows = 50L,
    maxcols = 6L,
    type = "sae",
    offset = 0.1,
    cex.var = 0.8,
    mar = c(0.1, 2.1, 5.1, 0.1)
)
```

Arguments

n.se

sae objects, dc_summary objects (output by the summary method for simulation objects of package **mcmcsae**), or lists. The first object must be a sae object. In case of a list the components used are those with name est for point estimates, se for standard error based intervals or lower and upper for custom intervals. Instead of dc_summary objects matrix objects are also supported as long as they contain columns named "Mean" and "SD" as do dc_summary objects. Named parameters of other types that do not match any other argument names are passed to lower-level plot functions.

number of standard errors below and above the point estimates to use for error bars. By default equal to 1. This only refers to the objects of class dc_summary

and sae.

est.names labels to use in the legend for the components of the . . . argument

sort.by vector by which to sort the coefficients, referring to the first object passed.

decreasing if TRUE, sort in decreasing order (default).

index vector of names or indices of the selected areas to be plotted.

maxrows maximum number of rows in a column.

plot.weights 17

maxcols	maximum number of columns of estimates on a page.
type	"sae" for small area estimates (default), "coef" for coefficients, "raneff" for random effects.
offset	space used between plots of multiple estimates for the same area.
cex.var	the fontsize of the variable names, default=0.8.
mar	a numerical vector of the form c(bottom, left, top, right) which gives the number of lines of margin to be specified on the four sides of the plot.

plot.weights

Plot method for objects of class weights.

Description

Plot method for objects of class weights.

Usage

```
## S3 method for class 'weights'
plot(
    x,
    log = FALSE,
    breaks = "Scott",
    main = "Distribution of weights",
    xlab = if (log) "log(weight)" else "weight",
    ylab = "frequency",
    col = "cyan",
    ...
)
```

Arguments

```
object of class weights as returned by function uweights.
Χ
log
                   whether to log-transform the weights.
breaks
                   breaks argument of function hist. Default is "Scott".
main
                   main title of plot.
xlab
                   x-axis label.
ylab
                   y-axis label.
col
                   colour.
                   additional arguments passed to hist.
. . .
```

See Also

```
uweights, summary.weights
```

18 sae-class

print.sae

Print method for objects of class sae.

Description

Print method for objects of class sae.

Usage

```
## S3 method for class 'sae'
print(x, digits = max(3L, getOption("digits") - 3L), ...)
```

Arguments

x object of class sae.

digits number of digits to display.

... additional arguments passed to print.default.

sae-class

S3 class for the fitted model and SAE outcomes.

Description

Functions fSAE, fSurvReg, fSAE.Area and fSAE.Unit return an object of class sae. It contains information on the model fit as well as the small area estimates, error estimates and a few model selection measures. The functions listed below extract the main components from an object of class sae.

EST(x, type="sae", tot=FALSE) return the vector of small area estimates of sae object x. Alternatively, with type "coef" or "raneff" fixed or random effect estimates are returned. If 'tot=TRUE' and 'type="sae"' estimates for area population totals instead of means are returned.

MSE(x, type="sae", tot=FALSE) return the vector of mean squared errors of sae object x. Alternatively, with type "coef" or "raneff" MSEs of fixed or random effects are returned. If 'tot=TRUE' and 'type="sae"' MSEs for area population totals instead of means are returned.

SE(x, type="sae", tot=FALSE) extract standard errors, i.e. square roots of MSEs.

RMSE(x, type="sae", tot=FALSE) alias for SE(x, type="sae", tot=FALSE)

relSE(x, type="sae") extract relative standard errors.

COV(x) extract the covariance matrix for the small area estimates.

COR(x) extract the correlation matrix for the small area estimates.

coef(x) coef method for sae objects; returns vector of fixed effects.

vcov(x) vcov method for sae objects; returns covariance matrix for fixed effects.

summary.weights 19

raneff(x, pop) return vector of random effects. If pop=TRUE returns a vector for predicted areas (zero for out-of-sample areas), otherwise a vector for in-sample areas.

raneff.se(x, pop) return vector of standard errors for random effects.

residuals(x) residuals method for sae objects; returns a vector of residuals.

fitted(x) fitted method for sae objects; returns a vector of fitted values.

se2(x) extracts within-area variance estimate.

sv2(x) extracts between-area variance estimate.

wDirect(x, pop) extract vector of weights of the survey regression components in the small area estimates. If pop=TRUE returns a vector for predicted areas (zero for out-of-sample areas), otherwise a vector for in-sample areas.

synthetic(x) extract vector of synthetic estimates.

CV(x) extract leave-one-out cross-validation measure.

cAIC(x) extract conditional AIC measure.

R2(x) extract unit-level R-squared goodness-of-fit measure.

Other components include

relErrM, relErrV relative numerical integration errors in estimates and MSEs, for method "HB".

Examples

```
d <- generateFakeData()

# compute small area estimates
sae <- fSAE(y0 ~ x + area2, data=d$sam, area="area", popdata=d$Xpop)

coef(sae) # fixed effects
raneff(sae) # random effects
sv2(sae) # between-area variance
se2(sae) # within-area variance
cAIC(sae) # conditional AIC</pre>
```

summary.weights

Summary method for objects of class weights.

Description

Summary method for objects of class weights.

Usage

```
## S3 method for class 'weights'
summary(object, ...)
```

20 uweights

Arguments

object of class weights as returned by function uweights.

... not used.

See Also

```
uweights, plot.weights
```

uweights Compute unit weights underlying the small area estimates or their ag-

gregate.

Description

The small area estimates can be interpreted as weighted sums of the response variable. This function computes the weights corresponding to the aggregated small area estimates or the weights corresponding to a specific small area estimate. The weights applied to the response variable need not exactly reproduce the Hierarchical Bayes estimate since the latter is averaged over the posterior distribution for the variance ratio whereas the weights are evaluated at the posterior mean. Under the default prior for the fixed effects, the weights applied to the design matrix reproduce the corresponding population numbers.

Usage

```
uweights(x, areaID = NULL, forTotal = FALSE)
```

Arguments

x sae object.

areaID if left unspecified (NULL), weights corresponding to the overall (aggregated) es-

timate are returned. Otherwise weights that reproduce the estimate for a specific

area are returned.

forTotal if FALSE weights will be divided by the corresponding population size.

Value

An object of class weights.

See Also

```
summary.weights, plot.weights
```

uweights 21

Examples

Index

```
summary.weights, 17, 19, 20
aggr, 2
                                                   sv2 (sae-class), 18
bench, 3
                                                   synthetic (sae-class), 18
cAIC (sae-class), 18
                                                   uweights, 17, 20, 20
coef.sae (sae-class), 18
COR (sae-class), 18
                                                   vcov.sae (sae-class), 18
COV (sae-class), 18
                                                   wDirect (sae-class), 18
CV (sae-class), 18
CVarea, 5
EST (sae-class), 18
fitted.sae (sae-class), 18
fSAE, 2, 6, 7, 18
fSAE.Area, 2, 6, 7, 9, 10, 18
fSAE.Unit, 2, 6-10, 10, 14, 18
fSurvReg, 2, 7, 8, 10, 14, 18
generateFakeData, 15
hbsae (hbsae-package), 2
hbsae-package, 2
hist, 17
integrate, 13
MSE (sae-class), 18
plot.sae, 16
plot.weights, 17, 20
print.sae, 18
R2 (sae-class), 18
raneff (sae-class), 18
relSE (sae-class), 18
residuals.sae (sae-class), 18
RMSE (sae-class), 18
sae-class, 18
SE (sae-class), 18
se2 (sae-class), 18
```